

D I G I T A L   C O M B A T   S I M U L A T O R

# DCS WORLD



## *ACTIVATION GUIDE*



THE FIGHTER COLLECTION



Eagle Dynamics

## ***ACTIVATION AND DEACTIVATION***

Using the activation number provided (on back of Quick Start Guide or provided by online store), you will be required to activate your game purchase prior to flying a mission. During the Activation process, the copy protection system will create a hardware profile of your system and compare that to your current system each time you start the game. If there has been a significant change to your computer, like replacing significant hardware items or changing your Operating System, you may be required to reactivate your purchase.

Each game license (disk) has 10 activations and 10 deactivations. You can activate your game up to 10 times. The number of installations is unlimited!

This game also allows Activations Automatically ("AAA") technology that enables you to create a new activation once every 31 days. This ensures that you can still play the game, even if Eagle Dynamics no longer exists someday. This function is enabled after all 10 default activations have been used.

If the copy protection system detects changes to your computer hardware/software as described below, an activation will be required. It's important to note that deactivations are utilized to save your activations when altering your PC hardware/software. Before conducting a PC upgrade/OS re-install, you can deactivate the product and when complete, reactivate without a loss of activations. Again though, you can install the game as much as you wish.

<http://www.star-force.com/support/users/deactivate/>

An activation will be required if the hardware/software changes exceed 12 points as rated below:

CPU ID: 13

Windows PID: 3

Computer Name: 3

Hard drive volume serial number: 3

MAC address: 6

RAM amount: 6

If you just uninstall the game and then reinstall it again on the same PC **without** reinstalling your operating system or changing hardware, you do not need to use a deactivation.

For further details on the copy protection system, please see the StarForce FAQ:

<http://www.star-force.com/support/users/group2.php>

In addition, a step-by-step (de)activation guide is available below:

<http://www.star-force.com/support/users/group4.php#6>


## Automatic Activation

The Automatic Activation method is the preferred method; an Internet connection is necessary.

Install the game to your computer. Launch it and fly a mission.

The Activation window will be displayed. Please follow the directions.

Enter your Activation Number which is printed on the DVD Quick Start Guide sticker or was provided to you via e-mail. Press the **Next** button.



The Automatic Activation is now complete.

## Other Activation Methods


If the automatic process fails, you may use one of two other activation means (Internet connection is necessary for both):

Activation via E-mail. Using this activation, you will be provided a hardware code that can be sent to the provided e-mail address for activation.

Activation via ProActive Web-site. A hardware code will be entered into the ProActive Web-site for activation.


### Activation via E-mail

If the automatic activation fails, press the **Other** link just below the edit-box.



Press the **Other** link

Press the **E-mail** tab in the Information window.



Press the **E-mail** tab

If you cannot send an e-mail now, copy your Serial Number, Hardware Code, and e-mail address shown in the Information window.

Warthog - Activation

Select preferable activation method:

Web Site E-mail

Serial Number (identifies product copy):  
FP-QF433A-GUN3Y7-YAV6VE-JHFU2K

Hardware code (identifies computer):  
QWVND-38W6NX-APHN7N-FVUD67-2S98NJ

For activation, submit specified Serial Number and Hardware Code to the e-mail address: [activation@digitalcombatsimulator.com](mailto:activation@digitalcombatsimulator.com) during one day. You will receive an email with your personal Activation Key in response.

To run the application, enter the Activation Key into this field and press "Next".

Next  
Back  
Exit

[Help](#)

When convenient, open your e-mail and send your Serial Number and Hardware Code to the indicated e-mail address. You will be sent an Activation Key shortly afterwards. Enter your Activation Key to the Activation field and press the **Next** button. Activation by e-mail will now be complete.

Activation via ProActive Web-site. If the automatic activation fails, press the **Other** link in the Activation window.

Warthog 64bit - Activation

This product requires activation. Enter your Serial Number and press "Next". Internet connection is required.

Next  
Exit

DY-Y2PYX7-YVLS8S-6NVNIX-C83N8S


If you don't have an Internet connection, you can perform activation by [other](#) means.

If you don't have a Serial Number, you can [buy](#) it.

You can [deactivate](#) the application on this computer. See Help for details. Afterwards this function will be available when running the application while holding Shift or Ctrl.

Press the **Other** link

Your Hardware Code is then displayed in the Activation window. Copy the Serial number and Hardware Code and save them to a safe location.



Press the [proactive.star-force.com/2.0/activate.php](\"http://proactive.star-force.com/2.0/activate.php\") link in the Activation window. In case your computer is not connected to the Internet, you can save your Serial Number and Hardware Code and go to the link using another computer.

Enter the Serial Number and the Hardware Code to the corresponding fields of the ProActive Web-site and press the **Get Activation Key** button.

Enter the Serial Number

Enter the Hardware Code

Choose language: [v] [Go]

## STAR FORCE® ProActive

### Product activation

Obtain an Activation Key to run and use the product on your computer. To obtain the key, you will need a Serial Number for the product and a Hardware Code generated automatically by the application at startup. To restore the deactivated product license, specify additionally a Deactivation Code obtained during deactivation of the product. If you have any questions, please contact the product technical support.

**Serial Number:**  
Enter your Serial Number for the product.   
[Serial Number parameters](#)

**Hardware Code:**  
Enter a Hardware Code

☐ **Deactivation Code:**  
To reactivate the product on your computer, enable this field and enter a Deactivation Code obtained during deactivation of the product.

Copyright © Protection Technology, 2003-2009. All rights reserved.

Press the button

You will then be provided your Activation Key. Copy it to a safe location.

Choose language: [v] [Go]

## STAR FORCE® ProActive

### Product activation


The Activation Key has been successfully generated. Write it down or save to a file for further input when running the application. Activation Key:

**License parameters:**  
Activations left: 7

If you have questions regarding product activation/deactivation, refer to the "Information" section or contact product technical support.

Copyright © Protection Technology, 2003-2009. All rights reserved.

Enter the Activation Key to the Activation field and press the **Next** button.



Activation via ProActive Web-site is now complete. If restrictions on game usage have been implemented, the Activation window will display the details. Press Ok to launch the game.

## Deactivation

To avoid using a product Activation, you may first Deactivate your installed game, make your changes, and then Activate again. You are provided 10 Deactivations.

You can launch the deactivation procedure by one of the two means:

The Automatic Deactivation


Deactivation via ProActive Web-site

### The Automatic Deactivation

Run the **<aircraft name>\_protect.exe** file, which is located in associated aircraft folder into DCS World\Mods\aircraft folder. For example, the P-51D Mustang: DCS World\Mods\aircrafts\P-51D\bin\x86\_64\p51\_protect.exe


Select the **Activate or deactivate application** command as displayed in the window, then press the **Next** button.






Select **Activate or deactivate product**

Press the **Deactivate** link in the displayed window (the Serial Number used to Activate the application is indicated in this window by default).




Press the **Deactivate** link


After pressing the **deactivate** link a window requesting deactivation confirmation is displayed.



Press the **Deactivate** button; the following message is then displayed.




Press **Yes** button to begin the deactivation process.



Confirm the application deactivation with the **OK** button.  
**The Automatic Deactivation is now complete.**


### Deactivation via ProActive Web-site

If automatic deactivation failed, or your computer is not connected to the Internet, a window suggesting deactivation appears. You click **other means** link in the Deactivation window.




Click **other means** link


Press **Yes** button to begin the deactivation process.




In the next window you should click <http://proactive.star-force.com/2.0/deactivate.php> link to go to ProActive Web-site.



Copy your Serial Number and Hardware Code shown in the window. When you get to the ProActive Web-site enter the indicated Serial Number and Hardware Code in the corresponding fields of the ProActive Web-site. And press the Deactivate button.



After that the following window with deactivation information will be displayed.



Deactivation via ProActive Web-site is now complete.

LAN and Internet play require Internet Authorization

Serial number